

---

# **PyCL Documentation**

***Release 0.1a***

**Ken Watford**

December 15, 2015



<b>1 Installation</b>	<b>3</b>
<b>2 Module API Reference</b>	<b>5</b>
<b>3 Indices and tables</b>	<b>33</b>
<b>Python Module Index</b>	<b>35</b>



PyCL is yet another OpenCL wrapper for Python. Its primary goal is simple: wrap OpenCL in such a way that as many Python implementations can use it as feasible. It is currently tested on CPython 2.{5,6,7}, 3.2, and PyPy 1.5. It is known to largely not work on Jython, whose ctypes library is still immature.

To achieve this, we eschew extension modules and dependencies outside of the standard library. Ideally things like NumPy arrays and PIL images should Just Work, but they shouldn't be required.

If you're looking to get actual work done in OpenCL, this probably isn't the distribution for you... yet. Before considering using PyCL for anything, give [PyOpenCL](#) a look. Its API is stable, its wrapper layer is fast C++, and it has fairly reasonable dependencies.

If you're looking to contribute, or just get the latest development release, take a look at our [repository](#).



---

## Installation

---

It's on PyPI, so installation should be as easy as:

```
pip install pycl
      -or-
easy_install pycl
```

But it's a single module and there's nothing to compile, so downloading it from PyPI or the repository and using it directly works too.

To actually use it, though, you'll need an OpenCL platform installed. If you're on Mac OS X 10.6 or later, you're already done. Otherwise, download and install an appropriate platform from [AMD](#), [Intel](#), or [NVIDIA](#).



---

## Module API Reference

---

Brief usage example:

```
from pycl import *
from array import array
source = '''
kernel void mxplusb(float m, global float *x, float b, global float *out) {
    int i = get_global_id(0);
    out[i] = m*x[i]+b;
}
'''

ctx = clCreateContext()
queue = clCreateCommandQueue(ctx)
program = clCreateProgramWithSource(ctx, source).build()
kernel = program['mxplusb']
kernel.argmaxes = (cl_float, cl_mem, cl_float, cl_mem)
x = array('f', range(10))
x_buf, in_evt = buffer_from_pyarray(queue, x, blocking=False)
y_buf = x_buf.empty_like_this()
run_evt = kernel(2, x_buf, 5, y_buf).on(queue, len(x), wait_for=in_evt)
y, evt = buffer_to_pyarray(queue, y_buf, wait_for=run_evt, like=x)
evt.wait()
print y
```

For Numpy users, see `buffer_from_ndarray()` and `buffer_to_ndarray()`.

Additionally, if run as a script, will print out a summary of your platforms and devices.

Most of the C typedefs are available as subclasses of Python ctypes datatypes. The spelling might be slightly different.

The various enumeration and bitfield types have attributes representing their defined constants (e.g. `CL_DEVICE_TYPE_GPU`). These constants are also available at the module level, in case you can't remember what type `CL_QUEUED` is supposed to be. They are all somewhat magical in that they'll make a reasonable effort to pretty-print themselves:

```
>>> cl_device_type.CL_DEVICE_TYPE_GPU | cl_device_type.CL_DEVICE_TYPE_CPU
CL_DEVICE_TYPE_CPU | CL_DEVICE_TYPE_GPU
>>> cl_mem_info(0x1100)
CL_MEM_TYPE
```

The types representing various object-like datastructures often have attributes so that you can view their infos without needing to call the appropriate `clGetThingInfo` function. They may have other methods and behaviors.

One last note about the datatypes: despite any appearance of magic and high-level function, these are just ctypes objects. It is entirely possible for you to assign things to the `value` attribute of the enum/bitfield constants or of object-

like items. Overwriting constants and clobbering pointers is generally a bad idea, though, so you should probably avoid it. (I tried vetoing assignment to .value, but PyPy didn't like that. So you're on your own.)

Wrapped OpenCL functions have their usual naming convention (`clDoSomething`). These aren't the naked C function pointers - you will find that the argument lists, return types, and exception raising are more in line with Python. Check the docstrings. That said, you can refer to the function pointer itself with the wrapped function's `call` attribute, which is how the functions themselves do it. The function pointer itself has argument type, return type, and error checking added in the usual ctypes manner.

The list of wrapped functions is *very* incomplete. Feel free to contribute if you need a function that hasn't been wrapped yet.

There are currently no plans to provide wrappers for OpenCL extensions (like OpenGL interop). Maybe later.

```
class pycl.cl_device_type
    Bitfield used by clCreateContextFromType() to create a context from one or more matching device types.
```

See also `cl_device.type` and `clGetDeviceInfo()`

```
CL_DEVICE_TYPE_ACCELERATOR
CL_DEVICE_TYPE_CPU
CL_DEVICE_TYPE_ALL
CL_DEVICE_TYPE_GPU
CL_DEVICE_TYPE_DEFAULT
```

```
class pycl.cl_errnum
```

A status code returned by most OpenCL functions. Exceptions exist for each error code and will be raised in the event that the code is flagged by any wrapper function. The exception names are formed by removing the 'CL', title-casing the words, removing the underscores, and appending 'Error' to the end. Some of these are a little redundant, like `BuildProgramFailureError`.

And no, there is no `SuccessError`.

```
CL_PROFILING_INFO_NOT_AVAILABLE
CL_INVALID_KERNEL_DEFINITION
CL_INVALID_VALUE
CL_INVALID_PROGRAM_EXECUTABLE
CL_INVALID_IMAGE_SIZE
CL_INVALID_WORK_DIMENSION
CL_INVALID_EVENT
CL_BUILD_PROGRAM_FAILURE
CL_INVALID_WORK_GROUP_SIZE
CL_MEM_COPY_OVERLAP
CL_INVALID_PROGRAM
CL_INVALID_COMMAND_QUEUE
CL_INVALID_KERNEL_NAME
CL_INVALID_GL_SHAREGROUP_REFERENCE_KHR
CL_DEVICE_NOT_AVAILABLE
```

`CL_INVALID_QUEUE_PROPERTIES`  
`CL_INVALID_CONTEXT`  
`CL_INVALID_KERNEL_ARGS`  
`CL_OUT_OF_HOST_MEMORY`  
`CL_INVALID_BUILD_OPTIONS`  
`CL_MAP_FAILURE`  
`CL_INVALID_KERNEL`  
`CL_INVALID_GLOBAL_WORK_SIZE`  
`CL_IMAGE_FORMAT_MISMATCH`  
`CL_KERNEL_ARG_INFO_NOT_AVAILABLE`  
`CL_INVALID_GL_OBJECT`  
`CL_MISALIGNED_SUB_BUFFER_OFFSET`  
`CL_INVALID_OPERATION`  
`CL_INVALID_PLATFORM`  
`CL_INVALID_DEVICE_TYPE`  
`CL_INVALID_PROPERTY`  
`CL_INVALID_ARG_VALUE`  
`CL_LINKER_NOT_AVAILABLE`  
`CL_INVALID_EVENT_WAIT_LIST`  
`CL_OUT_OF_RESOURCES`  
`CL_INVALID_DEVICE`  
`CL_EXEC_STATUS_ERROR_FOR_EVENTS_IN_WAIT_LIST`  
`CL_INVALID_ARG_SIZE`  
`CL_INVALID_BUFFER_SIZE`  
`CL_DEVICE_NOT_FOUND`  
`CL_INVALID_WORK_ITEM_SIZE`  
`CL_INVALID_MIP_LEVEL`  
`CL_INVALID_MEM_OBJECT`  
`CL_SUCCESS`  
`CL_INVALID_SAMPLER`  
`CL_INVALID_HOST_PTR`  
`CL_COMPILE_PROGRAM_FAILURE`  
`CL_COMPILER_NOT_AVAILABLE`  
`CL_INVALID_BINARY`  
`CL_DEVICE_PARTITION_FAILED`  
`CL_MEM_OBJECT_ALLOCATION_FAILURE`

```
CL_INVALID_IMAGE_FORMAT_DESCRIPTOR  
CL_LINK_PROGRAM_FAILURE  
CL_IMAGE_FORMAT_NOT_SUPPORTED  
CL_INVALID_ARG_INDEX  
CL_INVALID_GLOBAL_OFFSET
```

```
class pycl.cl_platform_info
```

The set of possible parameter names used with the `clGetPlatformInfo()` function.

```
CL_PLATFORM_PROFILE  
CL_PLATFORM_EXTENSIONS  
CL_PLATFORM_VENDOR  
CL_PLATFORM_VERSION  
CL_PLATFORM_NAME
```

```
class pycl.cl_device_info
```

The set of possible parameter names used with the `clGetDeviceInfo()` function.

```
CL_DEVICE_IMAGE2D_MAX_HEIGHT  
CL_DEVICE_MAX_WORK_ITEM_DIMENSIONS  
CL_DEVICE_IMAGE_SUPPORT  
CL_DEVICE_MIN_DATA_TYPE_ALIGN_SIZE  
CL_DEVICE_PARTITION_AFFINITY_DOMAIN  
CL_DEVICE_MEM_BASE_ADDR_ALIGN  
CL_DEVICE_ENDIAN_LITTLE  
CL_DEVICE_MAX_CONSTANT_BUFFER_SIZE  
CL_DEVICE_GLOBAL_MEM_CACHELINE_SIZE  
CL_DEVICE_PREFERRED_VECTOR_WIDTH_LONG  
CL_DEVICE_PREFERRED_VECTOR_WIDTH_SHORT  
CL_DEVICE_PREFERRED_VECTOR_WIDTH_INT  
CL_DEVICE_NATIVE_VECTOR_WIDTH_LONG  
CL_DEVICE_GLOBAL_MEM_SIZE  
CL_DEVICE_MAX_COMPUTE_UNITS  
CL_DEVICE_REFERENCE_COUNT  
CL_DEVICE_VENDOR  
CL_DEVICE_IMAGE_MAX_BUFFER_SIZE  
CL_DEVICE_PREFERRED_VECTOR_WIDTH_HALF  
CL_DRIVER_VERSION  
CL_DEVICE_DOUBLE_FP_CONFIG  
CL_DEVICE_NATIVE_VECTOR_WIDTH_HALF  
CL_DEVICE_IMAGE_PITCH_ALIGNMENT
```

```
CL_DEVICE_PROFILING_TIMER_RESOLUTION
CL_DEVICE_MAX_READ_IMAGE_ARGS
CL_DEVICE_QUEUE_PROPERTIES
CL_DEVICE_TYPE
CL_DEVICE_MAX_WORK_GROUP_SIZE
CL_DEVICE_IMAGE3D_MAX_DEPTH
CL_DEVICE_IMAGE_MAX_ARRAY_SIZE
CL_DEVICE_MAX_CONSTANT_ARGS
CL_DEVICE_IMAGE3D_MAX_HEIGHT
CL_DEVICE_PREFERRED_VECTOR_WIDTH_DOUBLE
CL_DEVICE_ADDRESS_BITS
CL_DEVICE_EXTENSIONS
CL_DEVICE_NATIVE_VECTOR_WIDTH_SHORT
CL_DEVICE_BUILT_IN KERNELS
CL_DEVICE_GLOBAL_MEM_CACHE_TYPE
CL_DEVICE_NATIVE_VECTOR_WIDTH_DOUBLE
CL_DEVICE_PLATFORM
CL_DEVICE_PREFERRED_VECTOR_WIDTH_CHAR
CL_DEVICE_PARTITION_TYPE
CL_DEVICE_PARENT_DEVICE
CL_DEVICE_IMAGE_BASE_ADDRESS_ALIGNMENT
CL_DEVICE_LINKER_AVAILABLE
CL_DEVICE_COMPILER_AVAILABLE
CL_DEVICE_LOCAL_MEM_SIZE
CL_DEVICE_AVAILABLE
CL_DEVICE_NATIVE_VECTOR_WIDTH_FLOAT
CL_DEVICE_NATIVE_VECTOR_WIDTH_INT
CL_DEVICE_HOST_UNIFIED_MEMORY
CL_DEVICE_GLOBAL_MEM_CACHE_SIZE
CL_DEVICE_PRINTF_BUFFER_SIZE
CL_DEVICE_PARTITION_MAX_SUB_DEVICES
CL_DEVICE_IMAGE3D_MAX_WIDTH
CL_DEVICE_VERSION
CL_DEVICE_NATIVE_VECTOR_WIDTH_CHAR
CL_DEVICE_IMAGE2D_MAX_WIDTH
CL_DEVICE_SINGLE_FP_CONFIG
```

```
CL_DEVICE_PROFILE
CL_DEVICE_HALF_FP_CONFIG
CL_DEVICE_PREFERRED_INTEROP_USER_SYNC
CL_DEVICE_NAME
CL_DEVICE_OPENCL_C_VERSION
CL_DEVICE_ERROR_CORRECTION_SUPPORT
CL_DEVICE_MAX_MEM_ALLOC_SIZE
CL_DEVICE_MAX_CLOCK_FREQUENCY
CL_DEVICE_PARTITION_PROPERTIES
CL_DEVICE_MAX_WORK_ITEM_SIZES
CL_DEVICE_EXECUTION_CAPABILITIES
CL_DEVICE_VENDOR_ID
CL_DEVICE_MAX_WRITE_IMAGE_ARGS
CL_DEVICE_PREFERRED_VECTOR_WIDTH_FLOAT
CL_DEVICE_MAX_PARAMETER_SIZE
CL_DEVICE_MAX_SAMPLERS
CL_DEVICE_LOCAL_MEM_TYPE
```

**class pycl.cl\_device\_fp\_config**

One of the possible return types from [clGetDeviceInfo\(\)](#). Bitfield identifying the floating point capabilities of the device.

```
CL_FP_ROUND_TO_ZERO
CL_FP_FMA
CL_FP_ROUND_TO_INF
CL_FP_DENORM
CL_FP_ROUND_TO_NEAREST
CL_FP_INF_NAN
CL_FP_SOFT_FLOAT
```

**class pycl.cl\_device\_mem\_cache\_type**

One of the possible return types from [clGetDeviceInfo\(\)](#). Describes the nature of the device's cache, if any.

```
CL_READ_WRITE_CACHE
CL_READ_ONLY_CACHE
CL_NONE
```

**class pycl.cl\_device\_local\_mem\_type**

One of the possible return types from [clGetDeviceInfo\(\)](#). Describes where 'local' memory lives in the device. Presumably, [CL\\_GLOBAL](#) means the device's local memory lives in the same address space as its global memory.

```
CL_LOCAL
```

---

```

CL_GLOBAL

class pycl.cl_device_exec_capabilities
    One of the possible return types from clGetDeviceInfo\(\). Bitfield identifying what kind of kernels can be executed. All devices can execute OpenCL C kernels, but some have their own native kernel types as well.

        CL_EXEC_KERNEL
        CL_EXEC_NATIVE_KERNEL

class pycl.cl_device_partition_property

        CL_DEVICE_PARTITION_BY_COUNTS
        CL_DEVICE_PARTITION_EQUALLY
        CL_DEVICE_PARTITION_BY_COUNTS_LIST_END
        CL_DEVICE_PARTITION_BY_AFFINITY_DOMAIN

class pycl.cl_device_affinity_domain

        CL_DEVICE_AFFINITY_DOMAIN_L2_CACHE
        CL_DEVICE_AFFINITY_DOMAIN_NUMA
        CL_DEVICE_AFFINITY_DOMAIN_L3_CACHE
        CL_DEVICE_AFFINITY_DOMAIN_L1_CACHE
        CL_DEVICE_AFFINITY_DOMAIN_L4_CACHE
        CL_DEVICE_AFFINITY_DOMAIN_NEXT_PARTITIONABLE

class pycl.cl_command_queue_properties
    Bitfield representing the properties of a command queue.

        CL_QUEUE_OUT_OF_ORDER_EXEC_MODE_ENABLE
        CL_QUEUE_PROFILING_ENABLE

class pycl.cl_context_properties
    If you find yourself looking at an array of these and need to make any sense of them... good luck!
    It's a list of key-value pairs, null-terminated. The keys are unsigned ints representing enum constants.
    CL_CONTEXT_PLATFORM (0x1084) is the most common one you'll see. I believe the rest are parts of extensions, such as the OpenGL interop extension.

    The meaning of the odd elements depends entirely on the enum that came just before it. In the case of CL_CONTEXT_PLATFORM, the value represents a pointer to a cl_platform object.

class pycl.cl_context_info
    Parameter names understood by clGetContextInfo\(\).

    Note that cl_context_inf.CL_CONTEXT_PLATFORM does not technically belong here, and the C-level code won't accept it. The wrapped version of clGetContextInfo\(\) will, however, recognize it and extract the appropriate value from the context's properties list.

        CL_GLX_DISPLAY_KHR
        CL_CONTEXT_PROPERTIES
        CL_GL_CONTEXT_KHR
        CL_CONTEXT_REFERENCE_COUNT

```

```
CL_CONTEXT_DEVICES
CL_EGL_DISPLAY_KHR
CL_WGL_HDC_KHR
CL_CGL_SHAREGROUP_KHR
CL_CONTEXT_PROPERTY_USE_CGL_SHAREGROUP_APPLE
CL_CONTEXT_NUM_DEVICES
CL_CONTEXT_PLATFORM

class pycl.cl_command_queue_info
    Parameter names understood by clGetCommandQueueInfo()

        CL_QUEUE_DEVICE
        CL_QUEUE_PROPERTIES
        CL_QUEUE_CONTEXT
        CL_QUEUE_REFERENCE_COUNT

class pycl.cl_channel_order
    Indicates the meanings of vector fields in an image.

        CL_RG
        CL_RGBA
        CL_R
        CL_RGB
        CL_ARGB
        CL_INTENSITY
        CL_RA
        CL_RGx
        CL_A
        CL_LUMINANCE
        CL_Rx
        CL_RGBx
        CL_BGRA

class pycl.cl_channel_type
    Indicates the type and size of image channels.

        CL_UNORM_SHORT_555
        CL_SNORM_INT8
        CL_SIGNED_INT8
        CL_UNORM_SHORT_565
        CL_SNORM_INT16
        CL_UNORM_INT16
        CL_SIGNED_INT32
```

---

```

CL_UNORM_INT_101010
CL_UNSIGNED_INT8
CL_HALF_FLOAT
CL_UNORM_INT8
CL_UNSIGNED_INT32
CL_FLOAT
CL_UNSIGNED_INT16
CL_SIGNED_INT16

```

```
class pycl.cl_mem_flags
```

Bitfield used when constructing a memory object. Indicates both the read/write status of the memory as well as how the memory interacts with whatever host pointer was provided. See the OpenCL [docs](#) for `clCreateBuffer()` for more information.

```

CL_MEM_USE_HOST_PTR
CL_MEM_WRITE_ONLY
CL_MEM_COPY_HOST_PTR
CL_MEM_READ_WRITE
CL_MEM_ALLOC_HOST_PTR
CL_MEM_READ_ONLY

```

```
class pycl.cl_mem_object_type
```

Possible return type for `clGetMemObjectInfo()`. Indicates the type of the memory object.

```

CL_MEM_OBJECT_IMAGE3D
CL_MEM_OBJECT_IMAGE2D
CL_MEM_OBJECT_BUFFER

```

```
class pycl.cl_mem_info
```

Parameter names accepted by `clGetMemObjectInfo()`

```

CL_MEM_REFERENCE_COUNT
CL_MEM_TYPE
CL_MEM_ASSOCIATED_MEMOBJECT
CL_MEM_CONTEXT
CL_MEM_OFFSET
CL_MEM_MAP_COUNT
CL_MEM_HOST_PTR
CL_MEM_SIZE
CL_MEM_FLAGS

```

```
class pycl.cl_mem_migration_flags
```

The set of possible parameter names used with the `clEnqueueMigrateMemObjects()` function.

```

CL_MIGRATE_MEM_OBJECT_CONTENT_UNDEFINED
CL_MIGRATE_MEM_OBJECT_HOST

```

**class `pycl.cl_image_info`**

Parameter names accepted by `clGetImageInfo()`

`CL_IMAGE_HEIGHT`  
`CL_IMAGE_SLICE_PITCH`  
`CL_IMAGE_FORMAT`  
`CL_IMAGE_ELEMENT_SIZE`  
`CL_IMAGE_WIDTH`  
`CL_IMAGE_DEPTH`  
`CL_IMAGE_ROW_PITCH`

**class `pycl.cl_buffer_create_type`**

Parameter type for `clCreateSubBuffer()` that indicates how the subbuffer will be described.

The only supported value is `CL_BUFFER_CREATE_TYPE_REGION`, which indicates the subbuffer will be a contiguous region as defined by a `cl_buffer_region` struct.

`CL_BUFFER_CREATE_TYPE_REGION`

**class `pycl.cl_addressing_mode`**

Addressing mode for sampler objects. Returned by `clGetSamplerInfo()`.

`CL_ADDRESS_MIRRORED_REPEAT`  
`CL_ADDRESS_CLAMP`  
`CL_ADDRESS_NONE`  
`CL_ADDRESS_CLAMP_TO_EDGE`  
`CL_ADDRESS_REPEAT`

**class `pycl.cl_filter_mode`**

Filter mode for sampler objects. Returned by `clGetSamplerInfo()`.

`CL_FILTER_NEAREST`  
`CL_FILTER_LINEAR`

**class `pycl.cl_sampler_info`**

Parameter names for `clGetSamplerInfo()`.

`CL_SAMPLER_REFERENCE_COUNT`  
`CL_SAMPLER_ADDRESSING_MODE`  
`CL_SAMPLER_FILTER_MODE`  
`CL_SAMPLER_NORMALIZED_COORDS`  
`CL_SAMPLER_CONTEXT`

**class `pycl.cl_map_flags`**

Read/write flags used for applying memory mappings to memory objects. See `clEnqueueMapBuffer()` and `clEnqueueMapImage()`.

`CL_MAP_WRITE`  
`CL_MAP_READ`

**class `pycl.cl_program_info`**

Parameter names for `clGetProgramInfo()`

```
CL_PROGRAM_REFERENCE_COUNT
CL_PROGRAM_DEVICES
CL_PROGRAM_NUM_DEVICES
CL_PROGRAM_CONTEXT
CL_PROGRAM_SOURCE
CL_PROGRAM_BINARIES
CL_PROGRAM_BINARY_SIZES

class pycl.cl_program_build_info
    Parameter names for clGetProgramBuildInfo\(\)
        CL_PROGRAM_BUILD_STATUS
        CL_PROGRAM_BUILD_LOG
        CL_PROGRAM_BUILD_OPTIONS

class pycl.cl_build_status
    Returned by clGetProgramBuildInfo\(\). Indicates build status for the program on the specified device.
        CL_BUILD_SUCCESS
        CL_BUILD_IN_PROGRESS
        CL_BUILD_NONE
        CL_BUILD_ERROR

class pycl.cl_kernel_info
    Parameter names for clGetKernelInfo\(\)
        CL_KERNEL_PROGRAM
        CL_KERNEL_NUM_ARGS
        CL_KERNEL_CONTEXT
        CL_KERNEL_REFERENCE_COUNT
        CL_KERNEL_FUNCTION_NAME

class pycl.cl_kernel_work_group_info
    Parameter names for clGetKernelWorkGroupInfo\(\)
        CL_KERNEL_COMPILE_WORK_GROUP_SIZE
        CL_KERNEL_LOCAL_MEM_SIZE
        CL_KERNEL_PREFERRED_WORK_GROUP_SIZE_MULTIPLE
        CL_KERNEL_PRIVATE_MEM_SIZE
        CL_KERNEL_WORK_GROUP_SIZE

class pycl.cl_event_info
    Parameter names for clGetEventInfo\(\)
        CL_EVENT_COMMAND_TYPE
        CL_EVENT_COMMAND_EXECUTION_STATUS
        CL_EVENT_COMMAND_QUEUE
        CL_EVENT_CONTEXT
```

```
CL_EVENT_REFERENCE_COUNT

class pycl.cl_command_type
    Command types recorded on events and returned by clGetEventInfo\(\).
        CL_COMMAND_NDRANGE_KERNEL
        CL_COMMAND_COPY_BUFFER
        CL_COMMAND_RELEASE_GL_OBJECTS
        CL_COMMAND_COPY_IMAGE
        CL_COMMAND_READ_BUFFER_RECT
        CL_COMMAND_COPY_BUFFER_RECT
        CL_COMMAND_WRITE_BUFFER
        CL_COMMAND_MARKER
        CL_COMMAND_WRITE_IMAGE
        CL_COMMAND_ACQUIRE_GL_OBJECTS
        CL_COMMAND_COPY_BUFFER_TO_IMAGE
        CL_COMMAND_READ_BUFFER
        CL_COMMAND_READ_IMAGE
        CL_COMMAND_UNMAP_MEM_OBJECT
        CL_COMMAND_NATIVE_KERNEL
        CL_COMMAND_MAP_IMAGE
        CL_COMMAND_COPY_IMAGE_TO_BUFFER
        CL_COMMAND_MAP_BUFFER
        CL_COMMAND_USER
        CL_COMMAND_WRITE_BUFFER_RECT
        CL_COMMAND_TASK

class pycl.cl_command_execution_status
    Status of the command associated with an event, returned by clGetEventInfo\(\).
        CL_QUEUED
        CL_COMPLETE
        CL_SUBMITTED
        CL_RUNNING

class pycl.cl_profiling_info
    Parameter names for clGetEventProfilingInfo\(\). Indicates the point in time of the event's life that
    should be queried.
        CL_PROFILING_COMMAND_SUBMIT
        CL_PROFILING_COMMAND_START
        CL_PROFILING_COMMAND_END
        CL_PROFILING_COMMAND_QUEUED
```

```
class pycl.cl_image_format
    Represents image formats. See clCreateImage2D().
    image_channel_order
        A cl_channel_order value
    image_channel_data_type
        A cl_channel_type value

class pycl.cl_buffer_region
    A buffer region has two fields: origin and size. Both are of type size_t.
    See clCreateSubBuffer() for usage.

exception pycl.OpenCLError
    The base class from which all of the (generated) OpenCL errors are descended. These exceptions correspond to the cl_errnum status codes.

class pycl.cl_event
    An OpenCL Event object. Returned by functions that add commands to a cl_command_queue, and often accepted (singly or in lists) by the wait_for argument of these functions to impose ordering.
    Use wait() to wait for a particular event to complete, or clWaitForEvents() to wait for several of them at once.
    These objects participate in OpenCL's reference counting scheme.

    queue
        The queue this event was emitted from.

    context
        The context this event exists within.

    type
        The type of command this event is linked to. See cl_command_type.

    status
        Execution status of the command the event is linked to. See cl_command_exec_status.

    reference_count
        Reference count for OpenCL garbage collection.

    wait()
        Blocks until this event completes.

pycl.clWaitForEvents(*events)
    Accepts several events and blocks until they all complete.

pycl.clGetEventInfo(event, param_name)
    Parameters param_name – An instance of cl_event_info.
    Event information can be more easily obtained by querying the properties of the event object, which in turn will call this function.

class pycl.cl_platform
    Represents an OpenCL Platform. Should not be directly instantiated by users of PyCL. Use clGetPlatformIDs() or the platform attribute of some OpenCL objects to procure a cl_platform instance.

    name
        Name of the platform. (str)
```

**vendor**

Vendor that distributes the platform. (str)

**version**

Platform version. Likely starts with ‘OpenCL 1.1’. (str)

**extensions**

Platform extensions supported. (list of str) Note that devices have their own set of extensions which should be inspected separately.

**profile**

One of ‘FULL\_PROFILE’ or ‘EMBEDDED\_PROFILE’.

**devices**

All devices available on this platform. (list of cl\_device)

**pycl.clGetPlatformIDs()**

Returns a list of *cl\_platform* objects available on your system. It should probably not be possible for this list to be empty if you are able to call this function.

```
>>> clGetPlatformIDs()  
(<cl_platform '...'>...)
```

**pycl.clGetPlatformInfo(*platform*, *param\_name*)**

**Parameters** *param\_name* – One of *cl\_platform\_info*.

*cl\_platform* objects have attributes that will call this for you, so you should probably use those instead of calling this directly.

```
>>> plat = clGetPlatformIDs()[0]  
>>> clGetPlatformInfo(plat, cl_platform_info.CL_PLATFORM_VERSION)  
'OpenCL ...'  
>>> plat.version  
'OpenCL ...'
```

Note that *CL\_PLATFORM\_EXTENSIONS* returns a string while the *extensions* attribute returns a list:

```
>>> clGetPlatformInfo(plat, cl_platform_info.CL_PLATFORM_EXTENSIONS)  
'...'  
>>> plat.extensions  
[...]
```

**class pycl.cl\_device**

Represents an OpenCL Device belonging to some platform. Should not be directly instantiated by users of PyCL. Use *clGetDeviceIDs()* or the *devices* attribute of some OpenCL objects to procure a *cl\_device* instances.

**address\_bits**

Same as calling *clGetDeviceInfo()* with *CL\_DEVICE\_ADDRESS\_BITS*

**available**

Same as calling *clGetDeviceInfo()* with *CL\_DEVICE\_AVAILABLE*

**built\_in\_kernels**

Same as calling *clGetDeviceInfo()* with *CL\_DEVICE\_BUILT\_IN\_KERNELS*

**compiler\_available**

Same as calling *clGetDeviceInfo()* with *CL\_DEVICE\_COMPILER\_AVAILABLE*

**double\_fp\_config**

Same as calling *clGetDeviceInfo()* with *CL\_DEVICE\_DOUBLE\_FP\_CONFIG*

**Endian\_little**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_ENDIAN_LITTLE`

**error\_correction\_support**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_ERROR_CORRECTION_SUPPORT`

**execution\_capabilities**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_EXECUTION_CAPABILITIES`

**global\_mem\_cache\_size**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_GLOBAL_MEM_CACHE_SIZE`

**global\_mem\_cache\_type**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_GLOBAL_MEM_CACHE_TYPE`

**global\_mem\_cacheline\_size**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_GLOBAL_MEM_CACHELINE_SIZE`

**global\_mem\_size**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_GLOBAL_MEM_SIZE`

**half\_fp\_config**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_HALF_FP_CONFIG`

**host\_unified\_memory**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_HOST_UNIFIED_MEMORY`

**image2d\_max\_height**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_IMAGE2D_MAX_HEIGHT`

**image2d\_max\_width**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_IMAGE2D_MAX_WIDTH`

**image3d\_max\_depth**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_IMAGE3D_MAX_DEPTH`

**image3d\_max\_height**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_IMAGE3D_MAX_HEIGHT`

**image3d\_max\_width**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_IMAGE3D_MAX_WIDTH`

**image\_base\_address\_alignment**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_IMAGE_BASE_ADDRESS_ALIGNMENT`

**image\_max\_array\_size**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_IMAGE_MAX_ARRAY_SIZE`

**image\_max\_buffer\_size**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_IMAGE_MAX_BUFFER_SIZE`

**image\_pitch\_alignment**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_IMAGE_PITCH_ALIGNMENT`

**image\_support**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_IMAGE_SUPPORT`

**linker\_available**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_LINKER_AVAILABLE`

**local\_mem\_size**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_LOCAL_MEM_SIZE`

**local\_mem\_type**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_LOCAL_MEM_TYPE`

**max\_clock\_frequency**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MAX_CLOCK_FREQUENCY`

**max\_compute\_units**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MAX_COMPUTE_UNITS`

**max\_constant\_args**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MAX_CONSTANT_ARGS`

**max\_constant\_buffer\_size**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MAX_CONSTANT_BUFFER_SIZE`

**max\_mem\_alloc\_size**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MAX_MEM_ALLOC_SIZE`

**max\_parameter\_size**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MAX_PARAMETER_SIZE`

**max\_read\_image\_args**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MAX_READ_IMAGE_ARGS`

**max\_samplers**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MAX_SAMPLERS`

**max\_work\_group\_size**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MAX_WORK_GROUP_SIZE`

**max\_work\_item\_dimensions**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MAX_WORK_ITEM_DIMENSIONS`

**max\_work\_item\_sizes**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MAX_WORK_ITEM_SIZES`

**max\_write\_image\_args**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MAX_WRITE_IMAGE_ARGS`

**mem\_base\_addr\_align**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MEM_BASE_ADDR_ALIGN`

**min\_data\_type\_align\_size**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_MIN_DATA_TYPE_ALIGN_SIZE`

**name**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_NAME`

**native\_vector\_width\_char**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_NATIVE_VECTOR_WIDTH_CHAR`

**native\_vector\_width\_double**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_NATIVE_VECTOR_WIDTH_DOUBLE`

**native\_vector\_width\_float**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_NATIVE_VECTOR_WIDTH_FLOAT`

**native\_vector\_width\_half**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_NATIVE_VECTOR_WIDTH_HALF`

**native\_vector\_width\_int**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_NATIVE_VECTOR_WIDTH_INT`

---

**native\_vector\_width\_long**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_NATIVE_VECTOR_WIDTH_LONG`

**native\_vector\_width\_short**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_NATIVE_VECTOR_WIDTH_SHORT`

**opencl\_c\_version**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_OPENCL_C_VERSION`

**parent\_device**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PARENT_DEVICE`

**partition\_affinity\_domain**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PARTITION_AFFINITY_DOMAIN`

**partition\_max\_sub\_devices**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PARTITION_MAX_SUB_DEVICES`

**partition\_properties**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PARTITION_PROPERTIES`

**partition\_type**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PARTITION_TYPE`

**platform**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PLATFORM`

**preferred\_interop\_user\_sync**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PREFERRED_INTEROP_USER_SYNC`

**preferred\_vector\_width\_char**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PREFERRED_VECTOR_WIDTH_CHAR`

**preferred\_vector\_width\_double**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PREFERRED_VECTOR_WIDTH_DOUBLE`

**preferred\_vector\_width\_float**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PREFERRED_VECTOR_WIDTH_FLOAT`

**preferred\_vector\_width\_half**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PREFERRED_VECTOR_WIDTH_HALF`

**preferred\_vector\_width\_int**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PREFERRED_VECTOR_WIDTH_INT`

**preferred\_vector\_width\_long**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PREFERRED_VECTOR_WIDTH_LONG`

**preferred\_vector\_width\_short**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PREFERRED_VECTOR_WIDTH_SHORT`

**printf\_buffer\_size**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PRINTF_BUFFER_SIZE`

**profile**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PROFILE`

**profiling\_timer\_resolution**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_PROFILING_TIMER_RESOLUTION`

**queue\_properties**  
Same as calling `clGetDeviceInfo()` with `CL_DEVICE_QUEUE_PROPERTIES`

**reference\_count**

Same as calling `clGetDeviceInfo()` with `CL_DEVICE_REFERENCE_COUNT`

**single\_fp\_config**

Same as calling `clGetDeviceInfo()` with `CL_DEVICE_SINGLE_FP_CONFIG`

**type**

Same as calling `clGetDeviceInfo()` with `CL_DEVICE_TYPE`

**vendor**

Same as calling `clGetDeviceInfo()` with `CL_DEVICE_VENDOR`

**vendor\_id**

Same as calling `clGetDeviceInfo()` with `CL_DEVICE_VENDOR_ID`

**version**

Same as calling `clGetDeviceInfo()` with `CL_DEVICE_VERSION`

`pycl.clGetDeviceIDs(platform=None, device_type=CL_DEVICE_TYPE_ALL)`

**Parameters**

- **platform** – The `cl_platform` whose devices you are interested in. If none is provided, the first platform on the system is used.
- **device\_type** – A `cl_device_type` bitfield indicating which devices should be listed. By default, all are listed.

```
>>> clGetDeviceIDs()
(<cl_device '...'>...)
```

`pycl.clGetDeviceInfo(device, param_name)`

**Parameters**

- **device** – A `cl_device`.
- **param\_name** – The `cl_device_info` item to be queried.

`cl_device` objects have attributes that will call this for you, so you should probably use those instead of calling this directly.

```
>>> d = clGetDeviceIDs()[0]
>>> clGetDeviceInfo(d, cl_device_info.CL_DEVICE_NAME)
'...'
>>> clGetDeviceInfo(d, cl_device_info.CL_DEVICE_TYPE)
CL_DEVICE_TYPE_...
>>> d.available
True
>>> d.max_work_item_sizes
(...)
```

Note that `CL_DEVICE_EXTENSIONS` returns a string while the `extensions` attribute returns a list:

```
>>> clGetDeviceInfo(d, cl_device_info.CL_DEVICE_EXTENSIONS)
'...'
>>> d.extensions
[...]
```

`class pycl.cl_context`

Represents an OpenCL Context instance.

Use `clCreateContext()` or `clCreateContextFromType()` to create a new context.

Participates in OpenCL's reference counting scheme.

#### **platform**

Retrieve the platform this context was made using. (`cl_platform`)

#### **reference\_count**

Reference count for OpenCL's internal garbage collector. (int) Using `clReleaseContext()` via `pycl` is an excellent way to generate segmentation faults.

#### **num\_devices**

Number of devices present in this particular context. (int)

#### **devices**

List of devices present in this particular context. (list of `cl_device`)

#### **properties**

Low-level ctypes array that is probably not user-interpretable.

`pycl.clCreateContext (devices=None, platform=None, other_props=None)`

Create a context with the given devices and platform.

#### Parameters

- **devices** – A list of devices. If None, the first device from the given platform is used.
- **platform** – If no platform or devices are provided, the first platform found will be used.  
If a device list is provided but no platform, the platform will be recovered from the devices.

If you just need a context and don't care what you get, calling with no arguments should hopefully get you something usable.

```
>>> clCreateContext()
<cl_context ...>
>>> one_device = clGetDeviceIDs() [0]
>>> clCreateContext(devices = [one_device])
<cl_context ...>
```

`pycl.clCreateContextFromType (device_type=CL_DEVICE_TYPE_DEFAULT, platform=None, other_props=None)`

Like `clCreateContext()`, but works by device type instead of expecting you to list the desired devices. This can, for instance, be used to create a context with GPU devices without the user having to pick a platform and inspect its device list.

#### Parameters

- **device\_type** – A `cl_device_type` field indicating which types of devices should be included.
- **platform** – A `cl_platform`. If no platform is provided, each platform will be tried in turn until a context with the specified device type can be created.

If you just need a context and don't care what you get, calling with no arguments should hopefully get you something usable.

```
>>> clCreateContextFromType(CL_DEVICE_TYPE_CPU | CL_DEVICE_TYPE_GPU)
<cl_context ...>
```

`pycl.clGetContextInfo (context, param_name)`

Retrieve context info.

#### Parameters

- **context** – `cl_context`.

- **param\_name** – One of the `cl_context_info` values.

`cl_context` objects have attributes that will call this for you, so you should probably use those instead of calling this directly.

```
>>> ctx = clCreateContext()
>>> clGetContextInfo(ctx, cl_context_info.CL_CONTEXT_DEVICES)
(<cl_device ...>...)
>>> ctx.platform
<cl_platform ...>
>>> ctx.reference_count
1
>>> ctx.properties
<...cl_context_properties_Array...>
```

## class `pycl.cl_command_queue`

Represents an OpenCL Command Queue instance. Should not be directly instantiated by users of PyCL. Use `clCreateCommandQueue()` to create a new queue.

### `context`

The context associated with the command queue. (`cl_context`)

### `device`

The device associated with the command queue. (`cl_device`)

### `properties`

Command queue property bitfield. (`cl_command_queue_properties`)

### `reference_count`

Reference count for OpenCL's garbage collector. (int)

`pycl.clCreateCommandQueue(context=None, device=None, properties=None)`

### Parameters

- **context** – `cl_context`. If not provided, one will be generated for you by calling `clCreateContext()` with no arguments. (it can later be retrieved via the `context` attribute)
- **device** – The `cl_device` that will be fed by this queue. If no device is provided, the first device in the context will be used.
- **properties** – A `cl_command_queue_properties` bitfield.

`pycl.clGetCommandQueueInfo(queue, param_name)`

### Parameters

- **queue** – `cl_command_queue`.
- **param\_name** – One of the `cl_command_queue_info` values.

```
>>> q = clCreateCommandQueue()
>>> q.context
<cl_context ...>
>>> q.device
<cl_device ...>
>>> q.properties
NONE
>>> q.reference_count
1
```

## class `pycl.cl_mem`

Represents an OpenCL memory object, typically a buffer or image.

See the individual types (`cl_buffer` and `cl_image`) for details. PyCL should probably never give you a direct instance of this class - treat it as abstract.

Memory objects are reference counted.

#### **size**

Memory size, in bytes.

#### **reference\_count**

Reference count for OpenCL garbage collector.

#### **map\_count**

Number of memory maps currently active for this object.

#### **hostptr**

Pointer to host address associated with this memory object at the time of creation. The meaning varies depending on the flags. (type is `void*`)

#### **flags**

The `cl_mem_flags` the object was created with.

#### **type**

The `cl_mem_type` of the object.

#### **context**

The `cl_context` the memory belongs to.

#### **empty\_like\_this()**

Creates an empty read/write buffer of the same size in the same context and returns it.

### **class pycl.cl\_buffer**

A subclass of `cl_mem` representing memory buffers. Create these with `clCreateBuffer()` or `clCreateSubBuffer()`

#### **base**

Base memory object (for sub-buffers)

#### **offset**

Offset, in bytes, from origin (for sub-buffers)

### **class pycl.cl\_image**

A subclass of `cl_mem` representing 2D or 3D images. Create these with `clCreateImage2D()` or `clCreateImage3D()`.

### **pycl.clCreateBuffer(context, size, flags=CL\_MEM\_READ\_WRITE, host\_ptr=None)**

#### **Parameters**

- **context** – `cl_context` that will own this memory.
- **size** – Desired size (in bytes) of the memory.
- **flags** – `cl_mem_flags` to control the memory.
- **host\_ptr** – `void*` to associate with this memory. The meaning of the association depends on the flags. (An integer representation of a pointer is fine).

See also `buffer_from_ndarray()`, `buffer_from_pyarray()`

### **pycl.clEnqueueReadBuffer(queue, mem, pointer, size=None, blocking=True, offset=0, wait\_for=None)**

Read from a `cl_mem` buffer into host memory.

#### **Parameters**

- **queue** – `cl_command_queue` to queue it on.

- **mem** – `cl_mem` to read from. Must be a buffer.
- **pointer** – `void*` pointer, the address to start writing into. (An integer representation of the pointer is fine).
- **size** – Number of bytes to read. If not specified, the entire buffer is read out, which might be hazardous if the place you’re writing it to isn’t big enough.
- **blocking** – Wait for the transfer to complete. Default is True. If False, you can use the returned event to check its status.
- **offset** – Offset in the buffer at which to start reading. Default is 0.
- **wait\_for** – `cl_event` (or a list of them) that must complete before the memory transfer will commence.

**Returns** `cl_event`

See also `buffer_to_ndarray()` and `buffer_to_pyarray()`.

```
>>> ctx = clCreateContext()
>>> queue = clCreateCommandQueue(ctx)
>>> array1 = (cl_int * 8)() # 32 bytes
>>> for i in range(8): array1[i] = i
>>> m = clCreateBuffer(ctx, 32)
>>> clEnqueueWriteBuffer(queue, m, array1, 32)
<cl_event ...
>
>>> array2 = (cl_int * 8)()
>>> clEnqueueReadBuffer(queue, m, array2, 32)
<cl_event ...
>>> [x.value for x in array2]
[0, 1, 2, 3, 4, 5, 6, 7]
```

```
pycl.clEnqueueWriteBuffer(queue, mem, pointer, size=None, blocking=True, offset=0,
                           wait_for=None)
```

Write to a `cl_mem` buffer from a location in host memory.

See `clEnqueueReadBuffer()` for the meanings of the parameters.

```
pycl.clEnqueueFillBuffer(queue, mem, pattern, offset=0, size=None, wait_for=None)
```

Enqueues a command to fill a buffer object with a pattern of a given pattern size.

TODO: Automatically determine pattern\_size, perhaps in a wrapper function?

```
pycl.clGetMemObjectInfo(mem, param_name)
```

#### Parameters

- **mem** – `cl_mem`
- **param\_name** – One of the `cl_mem_info` values.

Memory objects have properties that will retrieve these values for you, so you should probably use those.

```
class pycl.cl_program
```

Represents an OpenCL program, a container for kernels.

Use `clCreateProgramWithSource()` or `clCreateProgramWithBinary()` to make a program.

Remember to call `build()` to compile source programs.

You can retrieve a kernel like so: `>>> my_kernel = my_program['my_kernel'] # doctest: +SKIP`

Programs participate in reference counting.

**build(\*args, \*\*kw)**

Calls `clBuildProgram()` on the program, passing along any arguments you provide. The program itself will be returned, so you can use this idiom:

```
>>> source = 'kernel void foo(float bar) {}'
>>> ctx = clCreateContext()
>>> prog = clCreateProgramWithSource(ctx, source).build()
```

**context**

Returns the context the program exists within.

**reference\_count**

Reference count for OpenCL garbage collector.

**num\_devices**

Number of devices the program exists on.

**devices**

Devices on which the program exists.

**source**

Program's source code, if available.

**binary\_sizes**

Sizes, in bytes, of the binaries for each of the devices the program is compiled for.

**binaries**

Acquires the binaries for each device.

**build\_status(device=None)**

Retrieves the `cl_program_build_status` for one or more devices. See also `clGetProgramBuildInfo()`

**build\_options(device=None)**

Retrieves the build options, as a string, for one or more devices. See also `clGetProgramBuildInfo()`.

**build\_log(device=None)**

Returns the build log, as a string, for one or more devices. Mostly useful for checking compiler errors. See also `clGetProgramBuildInfo()`.

`pycl.clGetProgramInfo(program, param_name)`

**Parameters**

- **program** – `cl_program`
- **param\_name** – One of the `cl_program_info` values.

`pycl.clGetProgramBuildInfo(program, param_name, device=None)`

**Parameters**

- **program** – The `cl_program` to check.
- **param\_name** – One of the `cl_program_build_info` values.
- **device** – A `cl_device` instance, or list of them.

If a list of devices is provided, info will be returned for each of them in a list.

If no device is specified, all devices associated with the program will be used.

The `build_status()`, `build_options()`, and `build_log()` methods of program objects are equivalent to using this, so they may be preferable.

`pycl.clCreateProgramWithSource (context, source)`

#### Parameters

- **context** – Context in which the program will exist
- **source** – Source code, as a string.

Remember to call `build()` on the program.

`pycl.clBuildProgram (program, options=None, devices=None)`

Compiles a source program to run on one or more devices.

#### Parameters

- **program** – The `cl_program` to build.
- **options** – (optional) string with compiler options. See your OpenCL spec and platform provider's docs for possible values.
- **devices** – A list of devices to compile the program for. If not provided, it will be built for all devices in the context.

If the build fails, it will raise a `ProgramBuildFailureError` with details.

`class pycl.cl_kernel`

Represents an OpenCL kernel found in a `cl_program`.

After compiling a program, the kernels will be accessible as items whose keys are the kernel names.

Kernels are reference counted.

##### **name**

Name of the kernel function.

##### **program**

The `cl_program` this kernel lives in.

##### **context**

The `cl_context` this kernel lives in.

##### **num\_args**

Number of arguments required to call this kernel.

##### **reference\_count**

Reference count for OpenCL garbage collector.

##### **setarg (index, value=None, size=None)**

Sets one of the kernel's arguments.

#### Parameters

- **index** – 0-based argument number to set.
- **value** – Value to set it to. Can be a `cl_mem`, a Python int or float, or a `localmem` object to indicate local memory allocation.
- **size** – The size of the parameter, in bytes. PyCL will attempt to guess if you don't tell it here or by setting `argtypes`. Guessing is bad.

This does some extra work to try to ensure that the data is in a form suitable for the lower-level `clSetKernelArg()` call. The OpenCL API doesn't give us much help in determining what type an argument should be, so if possible you should set the elements of the kernel's `argtypes` field to a list of types. The types should be either `cl_mem`, `localmem`, a scalar type such as `cl_int`, or a ctypes structure type.

**argtypes**

Represents the data types of the kernel function arguments. There is no way to ask OpenCL for this information, so short of actually parsing the C code the only way to fill this in is to infer it from the way the user tries to call the kernel.

Since this is error prone, we encourage you to fill in the list yourself.

**on** (*queue*, *\*args*, *\*\*kw*)

Enqueue the kernel (hopefully after setting its arguments) upon a command queue. This is essentially a shortcut for `clEnqueueNDRangeKernel()`.

**work\_group\_size** (*device=None*)

The maximum size of workgroups for this kernel on the specified device.

**compile\_work\_group\_size** (*device=None*)

The work group size specified by the kernel source, if any. Otherwise, will return (0,0,0).

**local\_mem\_size** (*device=None*)

The amount of local memory that would be used by this kernel on the given device with its current argument set.

**preferred\_work\_group\_size\_multiple** (*device=None*)

Suggests a workgroup size multiplier for each dimension. That is, if a multiple is 8, then workgroup sizes should preferably be multiples of 8.

**private\_mem\_size** (*device=None*)

Amount of private memory needed to execute each workitem on the device.

**pycl.clCreateKernel** (*program*, *kernel\_name*)**Parameters**

- **program** – `cl_program`
- **kernel\_name** – String naming a kernel function in the program.

Using the the `program[kernel_name]` syntax is preferable.

**pycl.clGetKernelInfo** (*kernel*, *param\_name*)**Parameters**

- **kernel** – `cl_kernel`
- **param\_name** – One of the `cl_kernel_info` values.

Kernel objects have properties that call this function, so it is probably preferable to use those instead.

**pycl.clGetKernelWorkGroupInfo** (*kernel*, *param\_name*, *device=None*)**Parameters**

- **kernel** – `cl_kernel`
- **param\_name** – One of the `cl_kernel_work_group_info` values.
- **device** – `cl_device`. If no device is specified, the first device in the kernel's context is queried.

Retrieves information about the kernel specific to a particular device that it might be run on. This information is also available through specific methods of kernel objects, which may be preferable to calling this.

**class pycl.localmem** (*size*)

When a kernel defines an argument to be in local memory, no value can be passed in to that argument. Instead,

the size of the local memory is specified. While you could do this directly with `clSetKernelArg()`, localmem allows you to set this using the kernel call syntax. So if you had a kernel whose third argument was a local memory pointer, you could set the arguments like so:

```
>>> mykernel(x, y, localmem(1024))
```

localmem is also accepted in `argtypes`, in which case the kernel can be called using just the desired size:

```
>>> mykernel.argtypes = (cl_mem, cl_mem, localmem)
>>> mykernel(x, y, 1024)
```

`pycl.clSetKernelArg(kernel, index, value=None, size=None)`

#### Parameters

- **kernel** – `cl_kernel`
- **index** – 0-based argument index to set.
- **value** – Should be None or a pointer to a ctypes scalar or a `cl_mem` object. Does not accept `localmem`.
- **size** – Size in bytes of the referenced value. That is, if the argument is a 32-bit integer, this should be 4. If the argument is a `cl_mem`, it should be `sizeof(cl_mem)`.

Unlike most of the wrappers in PyCL, this one doesn't do much to help you out. Use `cl_kernel.setarg()` if you want some help setting individual arguments. Calling the kernel object itself with the desired argument sequence is more preferable still. Set `cl_kernel.argtypes` if it can't guess the types properly.

`pycl.clEnqueueNDRangeKernel(queue, kernel, gsize=(1, ), lsize=None, offset=None, wait_for=None)`

Enqueue a kernel for execution. The kernel's arguments should be set already. For a more idiomatic calling syntax, set the kernel arguments by calling it and use its `on()` method to queue it.

#### Parameters

- **queue** – `cl_command_queue` to enqueue it upon.
- **kernel** – The `cl_kernel` object you want to run.
- **gsize** – Global work size. A 1-, 2-, or 3-tuple of integers indicating the dimensions of the work to be done. A scalar is fine too. Default is a single work item.
- **lsize** – Local work size. Should have the same dimension as gsize. If None (the default), OpenCL will pick a size for you.
- **offset** – Global work item offset. By default, the global id of work items start at 0 in each dimension. Provide a tuple of the same dimension as gsize to offset the ids.
- **wait\_for** – A `cl_event` or list of them that should complete prior to this kernel's execution.

**Returns** `cl_event` which will identify when the kernel has completed.

Note that the OpenCL `clEnqueueTask()` function is equivalent to calling this function with the default gsize, lsize, and offset values, so we haven't bothered to wrap it.

`pycl.buffer_from_ndarray(queue, ary, buf=None, **kw)`

Creates (or simply writes to) an OpenCL buffer using the contents of a Numpy array.

#### Parameters

- **queue** – `cl_command_queue` to enqueue the write to.

- **ary** – `numpy.ndarray` object, or other object implementing the array interface. We haven't wrapped the rectangular read/write functions yet, so if the array isn't contiguous, a copy will be made. Note that the entirety of the provided array will be written, so be sure to slice it down to just the part you want to write.
- **buf** – `cl_mem` object. If not provided, one the size of the array will be created. In any event, it should hopefully be large enough to hold the provided array.

**Returns** (`buf, evt`), where `evt` is the `cl_event` returned by the write operation.

Any additional provided keyword arguments are passed along to `clEnqueueWriteBuffer()`.

`pycl.buffer_to_ndarray(queue, buf, out=None, like=None, dtype='uint8', shape=None, **kw)`  
Reads from an OpenCL buffer into an ndarray.

#### Parameters

- **queue** – The queue to put the read operation on.
- **buf** – The `cl_mem` to read from
- **out** – The `numpy.ndarray` to read into. If not provided, one will be created based on the following arguments. Unlike `buffer_from_array()`, this must currently be an actual contiguous ndarray object.
- **like** – Only relevant if no out array is provided. The new array will have the same shape and dtype as this value.
- **dtype** – Only relevant if no out array or `like` parameter are provided. A `numpy.dtype` or anything that can pass for one. Defaults to '`uint8`'.
- **shape** – Only relevant if no out array or `like` parameter are provided. Integer or tuple determining the array's shape. If no shape is given, the array will be 1d and will have a number of elements based on the buffer's size and the itemsize of the dtype.

**Returns** (`ary, evt`), where `evt` is the `cl_event` returned by the read operation.

Any further keyword arguments are passed directly to `clEnqueueReadBuffer()`.

`pycl.buffer_from_pyarray(queue, ary, buf=None, **kw)`  
Essentially the same as `buffer_from_ndarray()`, except that it accepts arrays from the `array` module in Python's standard library.

`pycl.buffer_to_pyarray(queue, buf, out=None, like=None, typecode='B', length=None, **kw)`  
Essentially the same as `buffer_to_ndarray()`, except that it produces arrays from the `array` module in Python's standard library. The `dtype` and `shape` parameters are replaced:

#### Parameters

- **typecode** – A character indicating the array typecode. See the documentation for the mappings to C data types. The default is 'B', for unsigned bytes.
- **length** – The number of elements that should be in the array. If not provided, it will be determined based on the buffer size and the size of the selected typecode.



## **Indices and tables**

---

- genindex
- modindex
- search



p

[pycl](#), 5



**A**

address\_bits (pycl.cl\_device attribute), 18  
argtypes (pycl.cl\_kernel attribute), 28  
available (pycl.cl\_device attribute), 18

**B**

base (pycl.cl\_buffer attribute), 25  
binaries (pycl.cl\_program attribute), 27  
binary\_sizes (pycl.cl\_program attribute), 27  
buffer\_from\_ndarray() (in module pycl), 30  
buffer\_from\_pyarray() (in module pycl), 31  
buffer\_to\_ndarray() (in module pycl), 31  
buffer\_to\_pyarray() (in module pycl), 31  
build() (pycl.cl\_program method), 26  
build\_log() (pycl.cl\_program method), 27  
build\_options() (pycl.cl\_program method), 27  
build\_status() (pycl.cl\_program method), 27  
built\_in\_kernels (pycl.cl\_device attribute), 18

**C**

CL\_A (pycl.cl\_channel\_order attribute), 12  
CL\_ADDRESS\_CLAMP (pycl.cl\_addressing\_mode attribute), 14  
CL\_ADDRESS\_CLAMP\_TO\_EDGE  
    (pycl.cl\_addressing\_mode attribute), 14  
CL\_ADDRESS\_MIRRORED\_REPEAT  
    (pycl.cl\_addressing\_mode attribute), 14  
CL\_ADDRESS\_NONE  
    (pycl.cl\_addressing\_mode attribute), 14  
CL\_ADDRESS\_REPEAT (pycl.cl\_addressing\_mode attribute), 14  
cl\_addressing\_mode (class in pycl), 14  
CL\_ARGB (pycl.cl\_channel\_order attribute), 12  
CL\_BGRA (pycl.cl\_channel\_order attribute), 12  
cl\_buffer (class in pycl), 25  
cl\_buffer\_create\_type (class in pycl), 14  
CL\_BUFFER\_CREATE\_TYPE\_REGION  
    (pycl.cl\_buffer\_create\_type attribute), 14  
cl\_buffer\_region (class in pycl), 17  
CL\_BUILD\_ERROR (pycl.cl\_build\_status attribute), 15

CL\_BUILD\_IN\_PROGRESS (pycl.cl\_build\_status attribute), 15  
CL\_BUILD\_NONE (pycl.cl\_build\_status attribute), 15  
CL\_BUILD\_PROGRAM\_FAILURE (pycl.cl\_errnum attribute), 6  
cl\_build\_status (class in pycl), 15  
CL\_BUILD\_SUCCESS (pycl.cl\_build\_status attribute), 15  
CL\_CGL\_SHAREGROUP\_KHR (pycl.cl\_context\_info attribute), 12  
cl\_channel\_order (class in pycl), 12  
cl\_channel\_type (class in pycl), 12  
CL\_COMMAND\_ACQUIRE\_GL\_OBJECTS  
    (pycl.cl\_command\_type attribute), 16  
CL\_COMMAND\_COPY\_BUFFER  
    (pycl.cl\_command\_type attribute), 16  
CL\_COMMAND\_COPY\_BUFFER\_RECT  
    (pycl.cl\_command\_type attribute), 16  
CL\_COMMAND\_COPY\_BUFFER\_TO\_IMAGE  
    (pycl.cl\_command\_type attribute), 16  
CL\_COMMAND\_COPY\_IMAGE  
    (pycl.cl\_command\_type attribute), 16  
CL\_COMMAND\_COPY\_IMAGE\_TO\_BUFFER  
    (pycl.cl\_command\_type attribute), 16  
cl\_command\_execution\_status (class in pycl), 16  
CL\_COMMAND\_MAP\_BUFFER  
    (pycl.cl\_command\_type attribute), 16  
CL\_COMMAND\_MAP\_IMAGE  
    (pycl.cl\_command\_type attribute), 16  
CL\_COMMAND\_MARKER  
    (pycl.cl\_command\_type attribute), 16  
CL\_COMMAND\_NATIVE\_KERNEL  
    (pycl.cl\_command\_type attribute), 16  
CL\_COMMAND\_NDRANGE\_KERNEL  
    (pycl.cl\_command\_type attribute), 16  
cl\_command\_queue (class in pycl), 24  
cl\_command\_queue\_info (class in pycl), 12  
cl\_command\_queue\_properties (class in pycl), 11  
CL\_COMMAND\_READ\_BUFFER  
    (pycl.cl\_command\_type attribute), 16  
CL\_COMMAND\_READ\_BUFFER\_RECT



CL\_DEVICE\_OPENCL\_C\_VERSION  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_LOCAL\_MEM\_SIZE  
 (pycl.cl\_device\_info attribute), 9  
 cl\_device\_local\_mem\_type (class in pycl), 10  
 CL\_DEVICE\_LOCAL\_MEM\_TYPE  
 (pycl.cl\_device\_info attribute), 10  
 CL\_DEVICE\_MAX\_CLOCK\_FREQUENCY  
 (pycl.cl\_device\_info attribute), 10  
 CL\_DEVICE\_MAX\_COMPUTE\_UNITS  
 (pycl.cl\_device\_info attribute), 8  
 CL\_DEVICE\_MAX\_CONSTANT\_ARGS  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_MAX\_CONSTANT\_BUFFER\_SIZE  
 (pycl.cl\_device\_info attribute), 8  
 CL\_DEVICE\_MAX\_MEM\_ALLOC\_SIZE  
 (pycl.cl\_device\_info attribute), 10  
 CL\_DEVICE\_MAX\_PARAMETER\_SIZE  
 (pycl.cl\_device\_info attribute), 10  
 CL\_DEVICE\_MAX\_READ\_IMAGE\_ARGS  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_MAX\_SAMPLERS (pycl.cl\_device\_info attribute), 10  
 CL\_DEVICE\_MAX\_WORK\_GROUP\_SIZE  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_MAX\_WORK\_ITEM\_DIMENSIONS  
 (pycl.cl\_device\_info attribute), 8  
 CL\_DEVICE\_MAX\_WORK\_ITEM\_SIZES  
 (pycl.cl\_device\_info attribute), 10  
 CL\_DEVICE\_MAX\_WRITE\_IMAGE\_ARGS  
 (pycl.cl\_device\_info attribute), 10  
 CL\_DEVICE\_MEM\_BASE\_ADDR\_ALIGN  
 (pycl.cl\_device\_info attribute), 8  
 cl\_device\_mem\_cache\_type (class in pycl), 10  
 CL\_DEVICE\_MIN\_DATA\_TYPE\_ALIGN\_SIZE  
 (pycl.cl\_device\_info attribute), 8  
 CL\_DEVICE\_NAME (pycl.cl\_device\_info attribute), 10  
 CL\_DEVICE\_NATIVE\_VECTOR\_WIDTH\_CHAR  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_NATIVE\_VECTOR\_WIDTH\_DOUBLE  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_NATIVE\_VECTOR\_WIDTH\_FLOAT  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_NATIVE\_VECTOR\_WIDTH\_HALF  
 (pycl.cl\_device\_info attribute), 8  
 CL\_DEVICE\_NATIVE\_VECTOR\_WIDTH\_INT  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_NATIVE\_VECTOR\_WIDTH\_LONG  
 (pycl.cl\_device\_info attribute), 8  
 CL\_DEVICE\_NATIVE\_VECTOR\_WIDTH\_SHORT  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_NOT\_AVAILABLE (pycl.cl\_errnum attribute), 6  
 CL\_DEVICE\_NOT\_FOUND (pycl.cl\_errnum attribute), 7  
 CL\_DEVICE\_OPENCL\_C\_VERSION  
 (pycl.cl\_device\_info attribute), 10  
 CL\_DEVICE\_PARENT\_DEVICE (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_PARTITION\_AFFINITY\_DOMAIN  
 (pycl.cl\_device\_info attribute), 8  
 CL\_DEVICE\_PARTITION\_BY\_AFFINITY\_DOMAIN  
 (pycl.cl\_device\_partition\_property attribute), 11  
 CL\_DEVICE\_PARTITION\_BY\_COUNTS  
 (pycl.cl\_device\_partition\_property attribute), 11  
 CL\_DEVICE\_PARTITION\_BY\_COUNTS\_LIST\_END  
 (pycl.cl\_device\_partition\_property attribute), 11  
 CL\_DEVICE\_PARTITION\_EQUALLY  
 (pycl.cl\_device\_partition\_property attribute), 11  
 CL\_DEVICE\_PARTITION FAILED (pycl.cl\_errnum attribute), 7  
 CL\_DEVICE\_PARTITION\_MAX\_SUB\_DEVICES  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_PARTITION\_PROPERTIES  
 (pycl.cl\_device\_info attribute), 10  
 cl\_device\_partition\_property (class in pycl), 11  
 CL\_DEVICE\_PARTITION\_TYPE (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_PLATFORM (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_PREFERRED\_INTEROP\_USER\_SYNC  
 (pycl.cl\_device\_info attribute), 10  
 CL\_DEVICE\_PREFERRED\_VECTOR\_WIDTH\_CHAR  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_PREFERRED\_VECTOR\_WIDTH\_DOUBLE  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_PREFERRED\_VECTOR\_WIDTH\_FLOAT  
 (pycl.cl\_device\_info attribute), 10  
 CL\_DEVICE\_PREFERRED\_VECTOR\_WIDTH\_HALF  
 (pycl.cl\_device\_info attribute), 8  
 CL\_DEVICE\_PREFERRED\_VECTOR\_WIDTH\_INT  
 (pycl.cl\_device\_info attribute), 8  
 CL\_DEVICE\_PREFERRED\_VECTOR\_WIDTH\_LONG  
 (pycl.cl\_device\_info attribute), 8  
 CL\_DEVICE\_PREFERRED\_VECTOR\_WIDTH\_SHORT  
 (pycl.cl\_device\_info attribute), 8  
 CL\_DEVICE\_PRINTF\_BUFFER\_SIZE  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_PROFILE (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_PROFILING\_TIMER\_RESOLUTION  
 (pycl.cl\_device\_info attribute), 8  
 CL\_DEVICE\_QUEUE\_PROPERTIES  
 (pycl.cl\_device\_info attribute), 9  
 CL\_DEVICE\_REFERENCE\_COUNT

(`pycl.cl_device_info` attribute), 8  
`CL_DEVICE_SINGLE_FP_CONFIG`  
    (`pycl.cl_device_info` attribute), 9  
`cl_device_type` (class in `pycl`), 6  
`CL_DEVICE_TYPE` (`pycl.cl_device_info` attribute), 9  
`CL_DEVICE_TYPE_ACCELERATOR`  
    (`pycl.cl_device_type` attribute), 6  
`CL_DEVICE_TYPE_ALL` (`pycl.cl_device_type` attribute), 6  
`CL_DEVICE_TYPE_CPU` (`pycl.cl_device_type` attribute), 6  
`CL_DEVICE_TYPE_DEFAULT` (`pycl.cl_device_type` attribute), 6  
`CL_DEVICE_TYPE_GPU` (`pycl.cl_device_type` attribute), 6  
`CL_DEVICE_VENDOR` (`pycl.cl_device_info` attribute), 8  
`CL_DEVICE_VENDOR_ID` (`pycl.cl_device_info` attribute), 10  
`CL_DEVICE_VERSION` (`pycl.cl_device_info` attribute), 9  
`CL_DRIVER_VERSION` (`pycl.cl_device_info` attribute), 8  
`CL_EGL_DISPLAY_KHR` (`pycl.cl_context_info` attribute), 12  
`cl_errnum` (class in `pycl`), 6  
`cl_event` (class in `pycl`), 17  
`CL_EVENT_COMMAND_EXECUTION_STATUS`  
    (`pycl.cl_event_info` attribute), 15  
`CL_EVENT_COMMAND_QUEUE` (`pycl.cl_event_info` attribute), 15  
`CL_EVENT_COMMAND_TYPE` (`pycl.cl_event_info` attribute), 15  
`CL_EVENT_CONTEXT` (`pycl.cl_event_info` attribute), 15  
`cl_event_info` (class in `pycl`), 15  
`CL_EVENT_REFERENCE_COUNT`  
    (`pycl.cl_event_info` attribute), 15  
`CL_EXEC_KERNEL` (`pycl.cl_device_exec_capabilities` attribute), 11  
`CL_EXEC_NATIVE_KERNEL`  
    (`pycl.cl_device_exec_capabilities` attribute), 11  
`CL_EXEC_STATUS_ERROR_FOR_EVENTS_IN_WAIT`  
    (`pycl.cl_errnum` attribute), 7  
`CL_FILTER_LINEAR` (`pycl.cl_filter_mode` attribute), 14  
`cl_filter_mode` (class in `pycl`), 14  
`CL_FILTER_NEAREST` (`pycl.cl_filter_mode` attribute), 14  
`CL_FLOAT` (`pycl.cl_channel_type` attribute), 13  
`CL_FP_DENORM` (`pycl.cl_device_fp_config` attribute), 10  
`CL_FP_FMA` (`pycl.cl_device_fp_config` attribute), 10  
`CL_FP_INF_NAN` (`pycl.cl_device_fp_config` attribute), 10  
`CL_FP_ROUND_TO_INF` (`pycl.cl_device_fp_config` attribute), 10  
`CL_FP_ROUND_TO_NEAREST`  
    (`pycl.cl_device_fp_config` attribute), 10  
`CL_FP_ROUND_TO_ZERO` (`pycl.cl_device_fp_config` attribute), 10  
`CL_FP_SOFT_FLOAT` (`pycl.cl_device_fp_config` attribute), 10  
`CL_GL_CONTEXT_KHR` (`pycl.cl_context_info` attribute), 11  
`CL_GLOBAL` (`pycl.cl_device_local_mem_type` attribute), 10  
`CL_GLX_DISPLAY_KHR` (`pycl.cl_context_info` attribute), 11  
`CL_HALF_FLOAT` (`pycl.cl_channel_type` attribute), 13  
`cl_image` (class in `pycl`), 25  
`CL_IMAGE_DEPTH` (`pycl.cl_image_info` attribute), 14  
`CL_IMAGE_ELEMENT_SIZE` (`pycl.cl_image_info` attribute), 14  
`cl_image_format` (class in `pycl`), 16  
`CL_IMAGE_FORMAT` (`pycl.cl_image_info` attribute), 14  
`CL_IMAGE_FORMAT_MISMATCH` (`pycl.cl_errnum` attribute), 7  
`CL_IMAGE_FORMAT_NOT_SUPPORTED`  
    (`pycl.cl_errnum` attribute), 8  
`CL_IMAGE_HEIGHT` (`pycl.cl_image_info` attribute), 14  
`cl_image_info` (class in `pycl`), 13  
`CL_IMAGE_ROW_PITCH` (`pycl.cl_image_info` attribute), 14  
`CL_IMAGE_SLICE_PITCH` (`pycl.cl_image_info` attribute), 14  
`CL_IMAGE_WIDTH` (`pycl.cl_image_info` attribute), 14  
`CL_INTENSITY` (`pycl.cl_channel_order` attribute), 12  
`CL_INVALID_ARG_INDEX` (`pycl.cl_errnum` attribute), 8  
`CL_INVALID_ARG_SIZE` (`pycl.cl_errnum` attribute), 7  
`CL_INVALID_ARG_VALUE` (`pycl.cl_errnum` attribute), 7  
`CL_INVALID_BINARY` (`pycl.cl_errnum` attribute), 7  
`CL_INVALID_BUFFER_SIZE` (`pycl.cl_errnum` attribute), 7  
`CL_INVALID_BUILD_OPTIONS` (`pycl.cl_errnum` attribute), 7  
`CL_INVALID_COMMAND_QUEUE` (`pycl.cl_errnum` attribute), 6  
`CL_INVALID_CONTEXT` (`pycl.cl_errnum` attribute), 7  
`CL_INVALID_DEVICE` (`pycl.cl_errnum` attribute), 7  
`CL_INVALID_DEVICE_TYPE` (`pycl.cl_errnum` attribute), 7  
`CL_INVALID_EVENT` (`pycl.cl_errnum` attribute), 6  
`CL_INVALID_EVENT_WAIT_LIST` (`pycl.cl_errnum` attribute), 7  
`CL_INVALID_GL_OBJECT` (`pycl.cl_errnum` attribute),

CL\_INVALID\_GL\_SHAREGROUP\_REFERENCE\_KHR  
     (`pycl.cl_errnum` attribute), 6  
 CL\_INVALID\_GLOBAL\_OFFSET (`pycl.cl_errnum` attribute), 8  
 CL\_INVALID\_GLOBAL\_WORK\_SIZE  
     (`pycl.cl_errnum` attribute), 7  
 CL\_INVALID\_HOST\_PTR (`pycl.cl_errnum` attribute), 7  
 CL\_INVALID\_IMAGE\_FORMAT\_DESCRIPTOR  
     (`pycl.cl_errnum` attribute), 7  
 CL\_INVALID\_IMAGE\_SIZE (`pycl.cl_errnum` attribute),  
     6  
 CL\_INVALID\_KERNEL (`pycl.cl_errnum` attribute), 7  
 CL\_INVALID\_KERNEL\_ARGS  
     (`pycl.cl_errnum` attribute), 7  
 CL\_INVALID\_KERNEL\_DEFINITION  
     (`pycl.cl_errnum` attribute), 6  
 CL\_INVALID\_KERNEL\_NAME  
     (`pycl.cl_errnum` attribute), 6  
 CL\_INVALID\_MEM\_OBJECT  
     (`pycl.cl_errnum` attribute), 7  
 CL\_INVALID\_MIP\_LEVEL (`pycl.cl_errnum` attribute),  
     7  
 CL\_INVALID\_OPERATION (`pycl.cl_errnum` attribute),  
     7  
 CL\_INVALID\_PLATFORM (`pycl.cl_errnum` attribute), 7  
 CL\_INVALID\_PROGRAM (`pycl.cl_errnum` attribute), 6  
 CL\_INVALID\_PROGRAM\_EXECUTABLE  
     (`pycl.cl_errnum` attribute), 6  
 CL\_INVALID\_PROPERTY (`pycl.cl_errnum` attribute), 7  
 CL\_INVALID\_QUEUE\_PROPERTIES (`pycl.cl_errnum` attribute), 6  
 CL\_INVALID\_SAMPLER (`pycl.cl_errnum` attribute), 7  
 CL\_INVALID\_VALUE (`pycl.cl_errnum` attribute), 6  
 CL\_INVALID\_WORK\_DIMENSION  
     (`pycl.cl_errnum` attribute), 6  
 CL\_INVALID\_WORK\_GROUP\_SIZE  
     (`pycl.cl_errnum` attribute), 6  
 CL\_INVALID\_WORK\_ITEM\_SIZE  
     (`pycl.cl_errnum` attribute), 7  
`cl_kernel` (class in `pycl`), 28  
 CL\_KERNEL\_ARG\_INFO\_NOT\_AVAILABLE  
     (`pycl.cl_errnum` attribute), 7  
 CL\_KERNEL\_COMPILE\_WORK\_GROUP\_SIZE  
     (`pycl.cl_kernel_work_group_info` attribute), 15  
 CL\_KERNEL\_CONTEXT  
     (`pycl.cl_kernel_info` attribute), 15  
 CL\_KERNEL\_FUNCTION\_NAME  
     (`pycl.cl_kernel_info` attribute), 15  
`cl_kernel_info` (class in `pycl`), 15  
 CL\_KERNEL\_LOCAL\_MEM\_SIZE  
     (`pycl.cl_kernel_work_group_info` attribute), 15  
 CL\_KERNEL\_NUM\_ARGS  
     (`pycl.cl_kernel_info` attribute), 15

CL\_KERNEL\_PREFERRED\_WORK\_GROUP\_SIZE\_MULTIPLE  
     (`pycl.cl_kernel_work_group_info` attribute), 15  
 CL\_KERNEL\_PRIVATE\_MEM\_SIZE  
     (`pycl.cl_kernel_work_group_info` attribute), 15  
 CL\_KERNEL\_PROGRAM  
     (`pycl.cl_kernel_info` attribute), 15  
 CL\_KERNEL\_REFERENCE\_COUNT  
     (`pycl.cl_kernel_info` attribute), 15  
`cl_kernel_work_group_info` (class in `pycl`), 15  
 CL\_KERNEL\_WORK\_GROUP\_SIZE  
     (`pycl.cl_kernel_work_group_info` attribute), 15  
 CL\_LINK\_PROGRAM\_FAILURE  
     (`pycl.cl_errnum` attribute), 8  
 CL\_LINKER\_NOT\_AVAILABLE  
     (`pycl.cl_errnum` attribute), 7  
 CL\_LOCAL  
     (`pycl.cl_device_local_mem_type` attribute),  
     10  
 CL\_LUMINANCE  
     (`pycl.cl_channel_order` attribute), 12  
 CL\_MAP\_FAILURE  
     (`pycl.cl_errnum` attribute), 7  
`cl_map_flags` (class in `pycl`), 14  
 CL\_MAP\_READ  
     (`pycl.cl_map_flags` attribute), 14  
 CL\_MAP\_WRITE  
     (`pycl.cl_map_flags` attribute), 14  
`cl_mem` (class in `pycl`), 24  
 CL\_MEM\_ALLOC\_HOST\_PTR  
     (`pycl.cl_mem_flags` attribute), 13  
 CL\_MEM\_ASSOCIATED\_MEMOBJECT  
     (`pycl.cl_mem_info` attribute), 13  
 CL\_MEM\_CONTEXT  
     (`pycl.cl_mem_info` attribute), 13  
 CL\_MEM\_COPY\_HOST\_PTR  
     (`pycl.cl_mem_flags` attribute), 13  
 CL\_MEM\_COPY\_OVERLAP  
     (`pycl.cl_errnum` attribute), 6  
`cl_mem_flags` (class in `pycl`), 13  
 CL\_MEM\_FLAGS  
     (`pycl.cl_mem_info` attribute), 13  
 CL\_MEM\_HOST\_PTR  
     (`pycl.cl_mem_info` attribute), 13  
`cl_mem_info` (class in `pycl`), 13  
 CL\_MEM\_MAP\_COUNT  
     (`pycl.cl_mem_info` attribute),  
     13  
`cl_mem_migration_flags` (class in `pycl`), 13  
 CL\_MEM\_OBJECT\_ALLOCATION\_FAILURE  
     (`pycl.cl_errnum` attribute), 7  
 CL\_MEM\_OBJECT\_BUFFER  
     (`pycl.cl_mem_object_type` attribute), 13  
 CL\_MEM\_OBJECT\_IMAGE2D  
     (`pycl.cl_mem_object_type` attribute), 13  
 CL\_MEM\_OBJECT\_IMAGE3D  
     (`pycl.cl_mem_object_type` attribute), 13  
`cl_mem_object_type` (class in `pycl`), 13  
 CL\_MEM\_OFFSET  
     (`pycl.cl_mem_info` attribute), 13  
 CL\_MEM\_READ\_ONLY  
     (`pycl.cl_mem_flags` attribute),  
     13  
 CL\_MEM\_READ\_WRITE  
     (`pycl.cl_mem_flags` attribute), 13  
 CL\_MEM\_REFERENCE\_COUNT  
     (`pycl.cl_mem_info`

attribute), 13  
CL\_MEM\_SIZE (pycl.cl\_mem\_info attribute), 13  
CL\_MEM\_TYPE (pycl.cl\_mem\_info attribute), 13  
CL\_MEM\_USE\_HOST\_PTR (pycl.cl\_mem\_flags attribute), 13  
CL\_MEM\_WRITE\_ONLY (pycl.cl\_mem\_flags attribute), 13  
CL\_MIGRATE\_MEM\_OBJECT\_CONTENT\_UNDEFINED (pycl.cl\_mem\_migration\_flags attribute), 13  
CL\_MIGRATE\_MEM\_OBJECT\_HOST (pycl.cl\_mem\_migration\_flags attribute), 13  
CL\_MISALIGNED\_SUB\_BUFFER\_OFFSET (pycl.cl\_errnum attribute), 7  
CL\_NONE (pycl.cl\_device\_mem\_cache\_type attribute), 10  
CL\_OUT\_OF\_HOST\_MEMORY (pycl.cl\_errnum attribute), 7  
CL\_OUT\_OF\_RESOURCES (pycl.cl\_errnum attribute), 7  
cl\_platform (class in pycl), 17  
CL\_PLATFORM\_EXTENSIONS (pycl.cl\_platform\_info attribute), 8  
cl\_platform\_info (class in pycl), 8  
CL\_PLATFORM\_NAME (pycl.cl\_platform\_info attribute), 8  
CL\_PLATFORM\_PROFILE (pycl.cl\_platform\_info attribute), 8  
CL\_PLATFORM\_VENDOR (pycl.cl\_platform\_info attribute), 8  
CL\_PLATFORM\_VERSION (pycl.cl\_platform\_info attribute), 8  
CL\_PROFILING\_COMMAND\_END (pycl.cl\_profiling\_info attribute), 16  
CL\_PROFILING\_COMMAND\_QUEUED (pycl.cl\_profiling\_info attribute), 16  
CL\_PROFILING\_COMMAND\_START (pycl.cl\_profiling\_info attribute), 16  
CL\_PROFILING\_COMMAND\_SUBMIT (pycl.cl\_profiling\_info attribute), 16  
cl\_profiling\_info (class in pycl), 16  
CL\_PROFILING\_INFO\_NOT\_AVAILABLE (pycl.cl\_errnum attribute), 6  
cl\_program (class in pycl), 26  
CL\_PROGRAM\_BINARIES (pycl.cl\_program\_info attribute), 15  
CL\_PROGRAM\_BINARY\_SIZES (pycl.cl\_program\_info attribute), 15  
cl\_program\_build\_info (class in pycl), 15  
CL\_PROGRAM\_BUILD\_LOG (pycl.cl\_program\_build\_info attribute), 15  
CL\_PROGRAM\_BUILD\_OPTIONS (pycl.cl\_program\_build\_info attribute), 15  
CL\_PROGRAM\_BUILD\_STATUS

(pycl.cl\_program\_build\_info attribute), 15  
CL\_PROGRAM\_CONTEXT (pycl.cl\_program\_info attribute), 15  
CL\_PROGRAM\_DEVICES (pycl.cl\_program\_info attribute), 15  
cl\_program\_info (class in pycl), 14  
CL\_PROGRAM\_NUM\_DEVICES (pycl.cl\_program\_info attribute), 15  
CL\_PROGRAM\_REFERENCE\_COUNT (pycl.cl\_program\_info attribute), 15  
CL\_PROGRAM\_SOURCE (pycl.cl\_program\_info attribute), 15  
CL\_QUEUE\_CONTEXT (pycl.cl\_command\_queue\_info attribute), 12  
CL\_QUEUE\_DEVICE (pycl.cl\_command\_queue\_info attribute), 12  
CL\_QUEUE\_OUT\_OF\_ORDER\_EXEC\_MODE\_ENABLE (pycl.cl\_command\_queue\_properties attribute), 11  
CL\_QUEUE\_PROFILING\_ENABLE (pycl.cl\_command\_queue\_properties attribute), 11  
CL\_QUEUE\_PROPERTIES (pycl.cl\_command\_queue\_info attribute), 12  
CL\_QUEUE\_REFERENCE\_COUNT (pycl.cl\_command\_queue\_info attribute), 12  
CL\_QUEUED (pycl.cl\_command\_execution\_status attribute), 16  
CL\_R (pycl.cl\_channel\_order attribute), 12  
CL\_RA (pycl.cl\_channel\_order attribute), 12  
CL\_READ\_ONLY\_CACHE (pycl.cl\_device\_mem\_cache\_type attribute), 10  
CL\_READ\_WRITE\_CACHE (pycl.cl\_device\_mem\_cache\_type attribute), 10  
CL\_RG (pycl.cl\_channel\_order attribute), 12  
CL\_RGB (pycl.cl\_channel\_order attribute), 12  
CL\_RGBA (pycl.cl\_channel\_order attribute), 12  
CL\_RGBx (pycl.cl\_channel\_order attribute), 12  
CL\_RGx (pycl.cl\_channel\_order attribute), 12  
CL\_RUNNING (pycl.cl\_command\_execution\_status attribute), 16  
CL\_Rx (pycl.cl\_channel\_order attribute), 12  
CL\_SAMPLER\_ADDRESSING\_MODE (pycl.cl\_sampler\_info attribute), 14  
CL\_SAMPLER\_CONTEXT (pycl.cl\_sampler\_info attribute), 14  
CL\_SAMPLER\_FILTER\_MODE (pycl.cl\_sampler\_info attribute), 14  
cl\_sampler\_info (class in pycl), 14  
CL\_SAMPLER\_NORMALIZED\_COORDS (pycl.cl\_sampler\_info attribute), 14  
CL\_SAMPLER\_REFERENCE\_COUNT

(`pycl.cl_sampler_info` attribute), 14  
`CL_SIGNED_INT16` (`pycl.cl_channel_type` attribute), 13  
`CL_SIGNED_INT32` (`pycl.cl_channel_type` attribute), 12  
`CL_SIGNED_INT8` (`pycl.cl_channel_type` attribute), 12  
`CL_SNORM_INT16` (`pycl.cl_channel_type` attribute), 12  
`CL_SNORM_INT8` (`pycl.cl_channel_type` attribute), 12  
`CL_SUBMITTED` (`pycl.cl_command_execution_status` attribute), 16  
`CL_SUCCESS` (`pycl.cl_errnum` attribute), 7  
`CL_UNORM_INT16` (`pycl.cl_channel_type` attribute), 12  
`CL_UNORM_INT8` (`pycl.cl_channel_type` attribute), 13  
`CL_UNORM_INT_101010` (`pycl.cl_channel_type` attribute), 12  
`CL_UNORM_SHORT_555` (`pycl.cl_channel_type` attribute), 12  
`CL_UNORM_SHORT_565` (`pycl.cl_channel_type` attribute), 12  
`CL_UNSIGNED_INT16` (`pycl.cl_channel_type` attribute), 13  
`CL_UNSIGNED_INT32` (`pycl.cl_channel_type` attribute), 13  
`CL_UNSIGNED_INT8` (`pycl.cl_channel_type` attribute), 13  
`CL_WGL_HDC_KHR` (`pycl.cl_context_info` attribute), 12  
`clBuildProgram()` (in module `pycl`), 28  
`clCreateBuffer()` (in module `pycl`), 25  
`clCreateCommandQueue()` (in module `pycl`), 24  
`clCreateContext()` (in module `pycl`), 23  
`clCreateContextFromType()` (in module `pycl`), 23  
`clCreateKernel()` (in module `pycl`), 29  
`clCreateProgramWithSource()` (in module `pycl`), 27  
`clEnqueueFillBuffer()` (in module `pycl`), 26  
`clEnqueueNDRangeKernel()` (in module `pycl`), 30  
`clEnqueueReadBuffer()` (in module `pycl`), 25  
`clEnqueueWriteBuffer()` (in module `pycl`), 26  
`clGetCommandQueueInfo()` (in module `pycl`), 24  
`clGetContextInfo()` (in module `pycl`), 23  
`clGetDeviceIDs()` (in module `pycl`), 22  
`clGetDeviceInfo()` (in module `pycl`), 22  
`clGetEventInfo()` (in module `pycl`), 17  
`clGetKernelInfo()` (in module `pycl`), 29  
`clGetKernelWorkGroupInfo()` (in module `pycl`), 29  
`clGetMemObjectInfo()` (in module `pycl`), 26  
`clGetPlatformIDs()` (in module `pycl`), 18  
`clGetPlatformInfo()` (in module `pycl`), 18  
`clGetProgramBuildInfo()` (in module `pycl`), 27  
`clGetProgramInfo()` (in module `pycl`), 27  
`clSetKernelArg()` (in module `pycl`), 30  
`clWaitForEvents()` (in module `pycl`), 17  
`compile_work_group_size()` (`pycl.cl_kernel` method), 29  
`compiler_available` (`pycl.cl_device` attribute), 18  
`context` (`pycl.cl_command_queue` attribute), 24  
`context` (`pycl.cl_event` attribute), 17  
`context` (`pycl.cl_kernel` attribute), 28  
`context` (`pycl.cl_mem` attribute), 25  
`context` (`pycl.cl_program` attribute), 27

## D

`device` (`pycl.cl_command_queue` attribute), 24  
`devices` (`pycl.cl_context` attribute), 23  
`devices` (`pycl.cl_platform` attribute), 18  
`devices` (`pycl.cl_program` attribute), 27  
`double_fp_config` (`pycl.cl_device` attribute), 18

## E

`empty_like_this()` (`pycl.cl_mem` method), 25  
`endian_little` (`pycl.cl_device` attribute), 18  
`error_correction_support` (`pycl.cl_device` attribute), 19  
`execution_capabilities` (`pycl.cl_device` attribute), 19  
`extensions` (`pycl.cl_platform` attribute), 18

## F

`flags` (`pycl.cl_mem` attribute), 25

## G

`global_mem_cache_size` (`pycl.cl_device` attribute), 19  
`global_mem_cache_type` (`pycl.cl_device` attribute), 19  
`global_mem_cacheline_size` (`pycl.cl_device` attribute), 19  
`global_mem_size` (`pycl.cl_device` attribute), 19

## H

`half_fp_config` (`pycl.cl_device` attribute), 19  
`host_unified_memory` (`pycl.cl_device` attribute), 19  
`hostptr` (`pycl.cl_mem` attribute), 25

## I

`image2d_max_height` (`pycl.cl_device` attribute), 19  
`image2d_max_width` (`pycl.cl_device` attribute), 19  
`image3d_max_depth` (`pycl.cl_device` attribute), 19  
`image3d_max_height` (`pycl.cl_device` attribute), 19  
`image3d_max_width` (`pycl.cl_device` attribute), 19  
`image_base_address_alignment` (`pycl.cl_device` attribute), 19  
`image_channel_data_type` (`pycl.cl_image_format` attribute), 17  
`image_channel_order` (`pycl.cl_image_format` attribute), 17  
`image_max_array_size` (`pycl.cl_device` attribute), 19  
`image_max_buffer_size` (`pycl.cl_device` attribute), 19  
`image_pitch_alignment` (`pycl.cl_device` attribute), 19  
`image_support` (`pycl.cl_device` attribute), 19

## L

`linker_available` (`pycl.cl_device` attribute), 19  
`local_mem_size` (`pycl.cl_device` attribute), 19

local\_mem\_size() (pycl.cl\_kernel method), 29  
local\_mem\_type (pycl.cl\_device attribute), 19  
localmem (class in pycl), 29

## M

map\_count (pycl.cl\_mem attribute), 25  
max\_clock\_frequency (pycl.cl\_device attribute), 20  
max\_compute\_units (pycl.cl\_device attribute), 20  
max\_constant\_args (pycl.cl\_device attribute), 20  
max\_constant\_buffer\_size (pycl.cl\_device attribute), 20  
max\_mem\_alloc\_size (pycl.cl\_device attribute), 20  
max\_parameter\_size (pycl.cl\_device attribute), 20  
max\_read\_image\_args (pycl.cl\_device attribute), 20  
max\_samplers (pycl.cl\_device attribute), 20  
max\_work\_group\_size (pycl.cl\_device attribute), 20  
max\_work\_item\_dimensions (pycl.cl\_device attribute), 20  
max\_work\_item\_sizes (pycl.cl\_device attribute), 20  
max\_write\_image\_args (pycl.cl\_device attribute), 20  
mem\_base\_addr\_align (pycl.cl\_device attribute), 20  
min\_data\_type\_align\_size (pycl.cl\_device attribute), 20

## N

name (pycl.cl\_device attribute), 20  
name (pycl.cl\_kernel attribute), 28  
name (pycl.cl\_platform attribute), 17  
native\_vector\_width\_char (pycl.cl\_device attribute), 20  
native\_vector\_width\_double (pycl.cl\_device attribute), 20  
native\_vector\_width\_float (pycl.cl\_device attribute), 20  
native\_vector\_width\_half (pycl.cl\_device attribute), 20  
native\_vector\_width\_int (pycl.cl\_device attribute), 20  
native\_vector\_width\_long (pycl.cl\_device attribute), 20  
native\_vector\_width\_short (pycl.cl\_device attribute), 21  
num\_args (pycl.cl\_kernel attribute), 28  
num\_devices (pycl.cl\_context attribute), 23  
num\_devices (pycl.cl\_program attribute), 27

## O

offset (pycl.cl\_buffer attribute), 25  
on() (pycl.cl\_kernel method), 29  
opencl\_c\_version (pycl.cl\_device attribute), 21  
OpenCLError, 17

## P

parent\_device (pycl.cl\_device attribute), 21  
partition\_affinity\_domain (pycl.cl\_device attribute), 21  
partition\_max\_sub\_devices (pycl.cl\_device attribute), 21  
partition\_properties (pycl.cl\_device attribute), 21  
partition\_type (pycl.cl\_device attribute), 21  
platform (pycl.cl\_context attribute), 23  
platform (pycl.cl\_device attribute), 21  
preferred\_interop\_user\_sync (pycl.cl\_device attribute), 21

preferred\_vector\_width\_char (pycl.cl\_device attribute), 21  
preferred\_vector\_width\_double (pycl.cl\_device attribute), 21  
preferred\_vector\_width\_float (pycl.cl\_device attribute), 21  
preferred\_vector\_width\_half (pycl.cl\_device attribute), 21  
preferred\_vector\_width\_int (pycl.cl\_device attribute), 21  
preferred\_vector\_width\_long (pycl.cl\_device attribute), 21  
preferred\_vector\_width\_short (pycl.cl\_device attribute), 21  
preferred\_work\_group\_size\_multiple() (pycl.cl\_kernel method), 29  
printf\_buffer\_size (pycl.cl\_device attribute), 21  
private\_mem\_size() (pycl.cl\_kernel method), 29  
profile (pycl.cl\_device attribute), 21  
profile (pycl.cl\_platform attribute), 18  
profiling\_timer\_resolution (pycl.cl\_device attribute), 21  
program (pycl.cl\_kernel attribute), 28  
properties (pycl.cl\_command\_queue attribute), 24  
properties (pycl.cl\_context attribute), 23  
pycl (module), 5

## Q

queue (pycl.cl\_event attribute), 17  
queue\_properties (pycl.cl\_device attribute), 21

## R

reference\_count (pycl.cl\_command\_queue attribute), 24  
reference\_count (pycl.cl\_context attribute), 23  
reference\_count (pycl.cl\_device attribute), 21  
reference\_count (pycl.cl\_event attribute), 17  
reference\_count (pycl.cl\_kernel attribute), 28  
reference\_count (pycl.cl\_mem attribute), 25  
reference\_count (pycl.cl\_program attribute), 27

## S

setarg() (pycl.cl\_kernel method), 28  
single\_fp\_config (pycl.cl\_device attribute), 22  
size (pycl.cl\_mem attribute), 25  
source (pycl.cl\_program attribute), 27  
status (pycl.cl\_event attribute), 17

## T

type (pycl.cl\_device attribute), 22  
type (pycl.cl\_event attribute), 17  
type (pycl.cl\_mem attribute), 25

## V

vendor (pycl.cl\_device attribute), 22  
vendor (pycl.cl\_platform attribute), 17

vendor\_id (pycl.cl\_device attribute), 22

version (pycl.cl\_device attribute), 22

version (pycl.cl\_platform attribute), 18

## W

wait() (pycl.cl\_event method), 17

work\_group\_size() (pycl.cl\_kernel method), 29